

Minimum Permissions To Run Loftware Applications

Description

Minimum user permissions required to run Loftware applications.

Article Number

2009314

Solution

Loftware applications requires the following user permissions:

- Read, Write, List Contents, Modify, Read and Execute access to the following:
 - C:\Program Files\Loftware Labeling (or the installation directory you create).
 - C:\Windows
 - C:\Windows\System32
- Full control of the following registry paths:
 - **HKEY_LOCAL_MACHINE\SOFTWARE\Loftware, Inc**
 - **HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\Loftware Notification Agent** to configure the Loftware Notification Agent.
 - **HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\LoftwareWebListener** to configure the WebListener.
 - **HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\WatchDogNT** to configure the Loftware Print Server.
- The default permissions of the "User" group.
- Client installations require access to **C:\Program Files\Loftware Clients** - or the equivalent folder if you installed using a language other than English.

Versions

Standalone, Terminal Server, and Citrix Metaframe installations of versions 7 and above

Environment

All supported installation environments.

Related Articles

Page: [Permissions to Grant Users Without Having to Grant Them SYSDBA for Oracle Connector \(Loftware Print Server Family Knowledge Base\)](#)

- [permissions](#)
- [oracle](#)
- [kb-how-to-article](#)

Page: [Minimum Permissions To Run Loftware Applications \(Loftware Print Server Family Knowledge Base\)](#)

- [run](#)
- [permissions](#)
- [kb-information-article](#)

Page: [Error M61429 You Do Not Have the Necessary Permissions to Save the Label in this Location \(Loftware Print Server Family Knowledge Base\)](#)

- [label](#)
- [design32](#)
- [permissions](#)
- [kb-troubleshooting-article](#)
- [administrator](#)
- [saving](#)
- [m61429](#)
- [61429](#)